

HEASP Guide

Version 1.10

Keith A. Arnaud

HEASARC
Code 662
Goddard Space Flight Center
Greenbelt, MD 20771
USA

Aug 2017

Contents

1	Introduction	3
2	Python module	5
2.1	Getting started	5
2.2	HEASP features not (yet) supported in Python	6
2.3	Spectrum example	6
2.4	Response example	7
2.5	Table model example	7
3	C++ classes and methods	11
3.1	Global defines	11
3.2	Spectra	12
3.2.1	Introduction and example	12
3.2.2	pha class	13
3.2.3	pha class public methods	14
3.2.4	Other pha routines	17
3.2.5	phaII class	17
3.2.6	phaII class public methods	18
3.3	Responses	19
3.3.1	Introduction and examples	19
3.3.2	rmf class	22
3.3.3	rmf class public methods	23
3.3.4	Other rmf routines	28
3.3.5	rmft class	28
3.3.6	rmft class public methods	29

3.3.7	arf class	30
3.3.8	arf class public methods	31
3.3.9	Other arf routines	32
3.3.10	arfII class	32
3.3.11	arfII class public methods	32
3.3.12	Other arfII routines	33
3.4	Table Models	34
3.4.1	Introduction and example	34
3.4.2	table classes	36
3.5	Grouping	39
3.5.1	grouping class	39
3.5.2	grouping class public methods	40
3.5.3	Other grouping routines	41
3.6	Utility routines	41
4	C interface	45
4.1	PHA files	45
4.1.1	PHA structure	45
4.1.2	PHA routines	46
4.2	RMF files	47
4.2.1	RMF structure	47
4.2.2	RMF routines	49
4.3	ARF files	50
4.3.1	ARF structure	50
4.3.2	ARF routines	51
4.4	Binning and utility	51
4.4.1	BinFactors structure	51
4.4.2	Binning and utility routines	52
A	Building programs using heasp	53
B	Ftools and Heasp	55
C	Error Codes	57

D	Change log	59
D.1	v1.10	59
D.1.1	General	59
D.1.2	pha, phaII	59
D.1.3	rmf	59
D.1.4	arf and arfII	60
D.1.5	table	60
D.1.6	grouping	60
D.2	v1.03	60
D.2.1	General	60
D.2.2	rmf	60
D.3	v1.02	60
D.3.1	General	60
D.3.2	pha, phaII	61
D.3.3	rmf	61
D.3.4	arf	61
D.4	v1.01	61
D.4.1	General	61
D.4.2	pha, phaII	62
D.4.3	rmf	62
D.4.4	table	62

Chapter 1

Introduction

HEASP is a C/C++/Python library to manipulate files associated with high energy astrophysics spectroscopic analysis. Currently this handles PHA, RMF, ARF and xspec table model files. The eventual plan is to be able to provide at least the functionality available in current ftools but from a single library.

The main code is written in C++ with classes for each file type. These classes and associated methods have been run through SWIG to produce Python code. C wrappers are provided for many of the C++ methods allowing simple use from C programs.

These C wrappers are compatible with an earlier C only version of HEASP with two exceptions: a) the include file required is now Cheasp.h instead of heasp.h; b) all routines which used to require a FITS file pointer now just require the filename. One consequence of b) is that files no longer need to be opened and closed by the calling program.

There are separate chapters describing the Python, C++, and C interfaces although users of Python should consult the C++ chapter for description of the classes.

Highlights of HEASP are :

- Read and write spectra, responses, arfs and table model files.
- Rebin spectra using grouping arrays.
- Compress responses by removing all elements below some value. Rebin responses in either energy or channel space based on a grouping array.
- Use a response to generate random channel numbers for a photon of a given energy.
- Sum both rmfs and arfs and multiply rmfs by arfs.
- Construct type II PHA or ARF from sets of spectra or arfs. Also extract individual spectra or arfs from type II files.

The latest version (1.10) changes the definition of the Real type from float to double for consistency with its use in the xspec code however most FITS data read by these routines are single-precision.

Chapter 2

Python module

2.1 Getting started

The standard HEAsoft build makes a Python module based on the HEASP C++ classes described in the next chapter. The standard HEAsoft initialization script adds the location of the HEASP Python module to PYTHONPATH. To load the module use

```
UNIX> python
>>>from heasp import *
```

If this produces name conflicts then loading the module by

```
UNIX> python
>>>import heasp
```

requires `heasp.` in front of all commands.

To set up an HEASP object first give a simple command such as

```
>>>sp = pha()
```

for a spectrum. This can then be read in and information about it displayed by

```
>>>sp.read("file1.pha")
>>>sp.disp()
```

Individual components of the object can be used by adding the component name to the object name without `()`. For instance:

```
>>>first = sp.FirstChannel
```


will place the first channel number in the variable first. The components of each class are given in the C++ chapter.

Components which are arrays can be used only through their individual element numbers. For instance:

```
>>>counts = []
>>>for i in xrange(sp.NumberChannels()):
...     counts.append(sp.Pha[i])
```

will place the contents of the PHA column in the list called counts. Going the other way, the current contents of the PHA column can be replaced by those in the counts list by:

```
>>>for i in xrange(sp.NumberChannels()):
...     sp.Pha[i] = counts[i]
```

2.2 HEASP features not (yet) supported in Python

At present the HEASP Python module does not support binary operations defined in the C++ classes such as the addition of two responses by `resp = resp1 + resp2`. What are supported are the unary equivalents so responses can be added by `resp1 += resp2`.

2.3 Spectrum example

The following Python example reads a type II PHA file, rebins the channels in each spectrum by a factor of 2 and writes out the result.

```
# read the spectrum
spectra = phaII()
spectra.read("testin.pha")

# loop round the spectra in the file
# rebinning by a factor of 2 then placing
# in the output spectra
output = phaII()
Nspectra = spectra.NumberSpectra()
groupInfo = grouping()

for i in xrange(Nspectra):
    spectrum = spectra.get(i)
    groupInfo.load(2,spectrum.NumberChannels())
    status = spectrum.rebinChannels(groupInfo)
    output.push(spectrum)
```

```
# write out the spectrum copying any extra keywords and extensions
# from testin.pha
output.write("testout.pha", "testin.pha")
```

2.4 Response example

The following Python example reads RMF and ARF files, removes all elements smaller than 10^{-6} from the RMF, multiplies the compressed RMF and the ARF, and writes out the result.

```
# read RMF and ARF
inputRMF = rmf()
inputRMF.read("testin.rmf")
inputARF = arf()
inputARF.read("testin.arf")

# compress the RMF
inputRMF.compress(1.0e-6)

# if the RMF and ARF are compatible then multiply them and write
# the result adding extra keywords and extensions from testin.rmf.
if inputRMF.checkCompatibility(inputARF) == 0:
    inputRMF *= inputARF
    inputRMF.write("testout.rsp", "testin.rmf")
```

2.5 Table model example

The following Python example sets up a table model grid with two parameters and one additional parameter (e.g. abundance). The parameters, energies and fluxes are given arbitrary values, in practice these could be read from text files.

```
test = table()

# set table descriptors and the energy array
test.ModelName = "Test"
test.ModelUnits = " "
test.isRedshift = True
test.isAdditive = True
test.isError = False

# set up the energies. note that the size is one greater
# than that of the array for the model fluxes
```

```
for i in xrange(100): test.Energies.append(0.1+i*0.1)

test.NumIntParams = 2
test.NumAddParams = 1

# define first parameter and give it 11 values ranging from
# 0.0 to 2.0 in steps of 0.2.

testpar = tableParameter()
testpar.Name = "param1"
testpar.InterpolationMethod = 0
testpar.InitialValue = 1.0
testpar.Delta = 0.1
testpar.Minimum = 0.0
testpar.Bottom = 0.0
testpar.Top = 2.0
testpar.Maximum = 2.0

for i in xrange(11): testpar.TabulatedValues.append(0.2*i)

# and push it onto the vector of parameters
test.pushParameter(testpar)

# define the second parameter and give it 5 values ranging from
# 4.6 to 5.4 in steps of 0.2.

testpar.clear()
testpar.Name = "param2"
testpar.InterpolationMethod = 0
testpar.InitialValue = 5.0
testpar.Delta = 0.1
testpar.Minimum = 4.6
testpar.Bottom = 4.6
testpar.Top = 5.4
testpar.Maximum = 5.4

for i in xrange(11): testpar.TabulatedValues.append(4.6+0.2*i)

# and push it onto the vector of parameters
test.pushParameter(testpar);

# define an additional parameter (usually the elemental abundance)
# does not require tabulated values.

testpar.clear()
```

```
testpar.Name = "addparam"
testpar.InterpolationMethod = 0
testpar.InitialValue = 0.0
testpar.Delta = 0.1
testpar.Minimum = 0.0
testpar.Bottom = 0.0
testpar.Top = 5.0
testpar.Maximum = 5.0

# and push it onto the vector of parameters
test.pushParameter(testpar)

# now set up the spectra. these are arbitrarily calculated, in a real program
# this step would read a file or call a routine.

addflux = []
testspec = tableSpectrum()

for i1 in xrange(11):
    for i2 in xrange(5):
        testspec.clear()
        testspec.ParameterValues.append(0.2*i1)
        testspec.ParameterValues.append(4.6+0.2*i2)
        addflux = []
        for j in xrange(99):
            testspec.Flux.append(0.2*i1+10*(4.6+0.2*i2)+j*0.1)
            addflux.append((i1+1)*(i2+1)+j*0.2)
        testspec.pushaddFlux(addflux)
        test.pushSpectrum(testspec)

# now write out the table.
test.write("test.mod");
```


Chapter 3

C++ classes and methods

3.1 Global defines

HEASP uses the include file “heasp.h” to set a number of global definitions.

```
typedef int Integer;  
typedef double Real;
```

set Integer and Real which are used in all classes. It also sets a couple of helpful definitions.

```
typedef vector<Integer> IntegerArray;  
typedef valarray<Real> RealArray;
```

This include file also contains the enumeration all error statuses.

```
enum{OK, NoSuchFile, NoData, NoChannelData, NoStatError, CannotCreate,  
      NoEnergyLo, NoEnergyHi, NoSpecresp, NoEboundsExt, NoEmin, NoEmax,  
      NoMatrixExt, NoNgrp, NoFchan, NoNchan, NoMatrix, CannotCreateMatrixExt,  
      CannotCreateEboundsExt, InconsistentGrouping, InconsistentEnergies,  
      InconsistentChannels, InconsistentUnits, UnknownXUnits, UnknownYUnits,  
      InconsistentNumelt, InconsistentNumgrp, InconsistentNumTableParams,  
      TableParamValueOutsideRange};
```

It also has some handy conversion factors.

```
#define KEVTOA 12.3984191
#define KEVTOHZ 2.4179884076620228e17
#define KEVTOERG 1.60217733e-9
#define KEVTOJY 1.60217733e14
```

3.2 Spectra

3.2.1 Introduction and example

Spectrum files can be manipulated using the `pha` and `phaII` classes. The latter is simply a vector of `pha` classes and is useful for handling type II PHA files. The grouping class and utility routines are also useful for some tasks. As an example the code below reads in a type II PHA file, bins up all the spectra by a factor of 2, then writes out the result. Note that the data types `Integer` and `Real` are defined in `heasp.h`.

```
#include "grouping.h"
#include "phaII.h"

using namespace std;

int main(int argc, char* argv[])
{
    string infile("testin.pha");
    string outfile("testout.pha");

    phaII inputSpectra;

    Integer Status(0);

    // read in all the spectra

    Status = inputSpectra.read(infile, 1);

    Integer Nspectra = inputSpectra.NumberSpectra();

    // loop round the spectra

    for (size_t i=0; i<(size_t)Nspectra; i++) {

        // set up the grouping object to rebin by a factor of 2
```

```

    grouping groupInfo;
    groupInfo.load(2, inputSpectra.phas[i].NumberChannels());

    // rebin this spectrum

    Status = inputSpectra.phas[i].rebinChannels(groupInfo);

}

// write the new spectra out copying extra keywords and extensions from
// the input file

Status = inputSpectra.write(outfile, infile);

exit(0);
}

```

3.2.2 pha class

```

class pha{
public:

    Integer FirstChannel;    // First legal channel number

    vector<Real> Pha;        // PHA data
    vector<Real> StatError;  // Statistical error
    vector<Real> SysError;   // Statistical error

    vector<Integer> Channel; // Channel number
    vector<Integer> Quality; // Data quality (0=good, 1=bad, 2=dubious,
                                //                    5=set bad by user)
    vector<Integer> Group;   // Data grouping (1=start of bin,
                                //                    -1=continuation of bin)

    vector<Real> AreaScaling; // Area scaling factor
    vector<Real> BackScaling; // Background scaling factor

    Real Exposure;          // Exposure time
    Real CorrectionScaling;  // Correction file scale factor

    Integer DetChans;       // Total legal number of channels
    bool Poisserr;          // If true, errors are Poisson
    string Datatype;        // "COUNT" for count data and "RATE" for count/sec
}

```



```

string PHAVersion;           // PHA extension format version

string Spectrumtype;        // "TOTAL", "NET", or "BKG"

string ResponseFile;        // Response filename
string AncillaryFile;       // Ancillary filename
string BackgroundFile;      // Background filename
string CorrectionFile;      // Correction filename

string FluxUnits;           // Units for Pha and StatError

string ChannelType;         // Value of CHANTYPE keyword
string Telescope;
string Instrument;
string Detector;
string Filter;
string Datamode;

vector<string> XSPECFilter; // Filter keywords

```

3.2.3 pha class public methods

- Integer read(string filename)

```
Integer read(string filename, Integer PHANumber)
```

```
Integer read(string filename, Integer PHANumber,
             Integer SpectrumNumber)
```

Read file into object. If PHANumber is given then look for the SPECTRUM extension with EXTVER=PHANumber. The third option is to read the pha from the SpectrumNumber row of a type II file.

- pha& operator= (const pha&)

Deep copy.

- Integer NumberChannels()

Return the size of vector|Real|s.

- string disp()

Display information about the spectrum - return as a string.

- void clear()

Clear information from the spectrum

- `string check()`

Check completeness and consistency of information in spectrum, if there is a problem then return diagnostic in string.

- `Integer write(string filename)`

`Integer write(string filename, string copyfilename)`

`Integer write(string filename, string copyfilename,
Integer HDUnumber)`

Write spectrum as type I file. If copyfilename is given then copy from it other HDUs and other keywords in the SPECTRUM extension. If HDUnumber is specified then use the SPECTRUM extension with EXTVER=HDUnumber in copyfilename. Note that if the output filename exists and already has a SPECTRUM extension then these methods will write an additional SPECTRUM extension.

- `pha& operator*= (const Real)`

Multiply by a constant.

- `pha& operator+= (const pha&)`

Add to another pha. If one or both of the pha have non-Poisson errors then they are added in quadrature. If systematic errors are present then the resulting pha has systematic errors equal to the maximum of those from the input pha. The exposures are added.

- `Integer checkCompatibility(const pha&)`

Check compatibility with another pha. This should be done before attempting to sum them.

- `Integer selectChannels(vector<Integer>& Start,
vector<Integer>& End)`

Select a subset of the channels

- `Integer setGrouping(grouping&)`

Set the pha grouping array from a grouping object.

- `grouping getMinCountsGrouping(const Integer MinCounts,
const Integer StartChannel, const Integer EndChannel)`

`grouping getMinCountsGrouping(const Integer MinCounts)`

Get grouping (optionally between channels StartChannel and EndChannel) using a minimum number of counts per bin

- `grouping getMinSNGrouping(const Real SignalToNoise,
const Integer StartChannel, const Integer EndChannel,
const pha& Background)`

```
grouping getMinSNGrouping(const Real SignalToNoise,
                          const pha& Background)
```

```
grouping getMinSNGrouping(const Real SignalToNoise,
                          const Integer StartChannel, const Integer EndChannel)
```

```
grouping getMinSNGrouping(const Real SignalToNoise)
```

Get grouping (optionally between channels StartChannel and EndChannel) using a minimum S/N. Optionally includes a background file as well.

- Integer rebinChannels(grouping&)

```
Integer rebinChannels(grouping&, string)
```

Rebin spectrum channels based on a grouping object. If no string is input then the resulting StatError is calculated by summing in quadrature. If a string is input then the resulting StatError is calculated based on the value of the input string. If it is PROPAGATE then summing in quadrature is used. If not, then GAUSS uses $1/\sqrt{\text{Pha}}$, POISS-0 sets Poisserr to true, POISS-1 uses $1 + \sqrt{N+0.75}$, POISS-2 uses $\sqrt{N-0.25}$, and POISS-3 uses the arithmetic mean of POISS-1 and POISS-2. In general, only the options PROPAGATE or POISS-0 should be used.

- Integer shiftChannels(Integer Start, Integer End, Real Shift)

```
Integer shiftChannels(Integer Start, Integer End,
                      Real Shift, Real Factor)
```

```
Integer shiftChannels(vector<Integer>& Start,
                      vector<Integer>& End, vector<Real>& Shift, vector<Real>&
                      Factor)
```

```
Integer shiftChannels(vector<Real>& ChannelLowEnergy,
                      vector<Real>& ChannelHighEnergy, Integer Start, Integer End,
                      Real Shift, Real Factor)
```

```
Integer shiftChannels(vector<Real>& ChannelLowEnergy,
                      vector<Real>& ChannelHighEnergy, vector<Integer>& Start,
                      vector<Integer>& End, vector<Real>& Shift, vector<Real>& Factor)
```

Shift counts in channels. Those counts between channels Start and End will be shifted by Shift channels and stretched by Factor. If the channel energies are given then Shift is assumed to be in energy, otherwise in channels. Total counts are conserved.

- Integer convertUnits(vector<Real>& ChannelLowEnergy,
vector<Real>& ChannelHighEnergy, string EnergyUnits)

Convert flux units from whatever they are currently to $\text{ph}/\text{cm}^2/\text{s}$. This requires as input the channel energy arrays from the rmf object and the string specifying their units. The allowed flux units are: $\text{ph}/\text{cm}^2/\text{s}/X$, where X is one of MeV, GeV, Hz, A, cm, um, nm; $\text{ergs}/\text{cm}^2/\text{s}$; $\text{ergs}/\text{cm}^2/\text{s}/X$, where X is one of Hz, A, cm, um, nm; Jy. The allowed energy units are keV, GeV, Hz, angstrom, cm, micron or nm.

3.2.4 Other pha routines

- pha operator+ (const pha& a, const pha& b)

Add pha a and b. If one or both of the pha have non-Poisson errors then they are added in quadrature. If systematic errors are present then the resulting pha has systematic errors equal to the maximum of those from the input pha. The exposures are added.

- Integer PHAtype(string filename, Integer PHANumber)

```
Integer PHAtype(string filename, Integer PHANumber,  
Integer& Status)
```

Return the type of a SPECTRUM extension.

- bool IsPHACounts(string filename, Integer PHANumber)

```
bool IsPHACounts(string filename, Integer PHANumber,  
Integer& Status)
```

Return true if the COUNTS column exists and is integer.

- Integer NumberofSpectra(string filename,
Integer PHANumber)

```
Integer NumberofSpectra(string filename,  
Integer PHANumber, Integer& Status)
```

Return the number of spectra in a type II SPECTRUM extension.

3.2.5 phaII class

```
class phaII{  
public:  
  
vector<pha> phas;           // vector of pha objects
```

3.2.6 phaII class public methods

- `Integer read(string filename)`

`Integer read(string filename, Integer PHANumber)`

`Integer read(string filename, Integer PHANumber,
vector<Integer> SpectrumNumber)`

Read a PHA type II file into an object. If PHANumber is given then read from the SPECTRUM extension with EXTVER=PHANumber. If the SpectrumNumber array is given then read those rows in the extension otherwise read all spectra.

- `phaII& operator= (const phaII&)`

Deep copy.

- `pha get(Integer number)`

Get pha object (counts from zero).

- `pha push(pha sp)`

Push pha object into phaII object

- `Integer NumberSpectra()`

Return the number of spectra in the object.

- `string disp()`

Display information about the spectra - return as a string.

- `void clear()`

Clear information about the spectra

- `string check()`

Check completeness and consistency of information in spectrum, if there is a problem then return diagnostic in string.

- `Integer write(string filename)`

`Integer write(string filename, string copyfilename)`

`Integer write(string filename, string copyfilename,
Integer HDUnumber)`

Write spectra as type II file. If copyfilename is given then copy from it other HDUs and other keywords in the SPECTRUM extension. If HDUnumber is specified then use the SPECTRUM extension with EXTVER=HDUnumber in copyfilename. Note that if the output filename exists and already has a SPECTRUM extension then these methods will write an additional SPECTRUM extension.

3.3 Responses

3.3.1 Introduction and examples

Response files come in two varieties: RMFs and ARFs. The former contain the response matrices describing the probability of a photon of a given energy being registered in a given channel of the spectrum. The latter describes the effective area versus energy. The `rmf` class is used for manipulating RMFs and the `arf` and `arfII` classes for manipulating ARFs. The `arfII` class is an analog of the `phaII` class and is useful for the case where an ARF file contains many individual effective area curves. The `rmft` class handles the transposed response matrix and is of limited use at present.

The example code below shows a program to read in an RMF file, to compress the matrix to remove any element below $1.0\text{e-}6$, to multiply the result by an ARF, and write a new RMF file.

```
#include "rmf.h"
#ifdef HAVE_arf
#include "arf.h"
#endif

using namespace std;

int main(int argc, char* argv[])
{
    string rmffile("testin.rmf");
    string arffile("testin.arf");
    string outfile("testout.rmf");

    rmf inputRMF, outputRMF;
    arf inputARF;

    Integer Status(0);

    // read in the RMF and the ARF

    Status = inputRMF.read(rmffile);
    Status = inputARF.read(arffile);

    // remove elements from the RMF with values < 1.0e-6

    Real threshold(1.0e-6);
    inputRMF.compress(threshold);

    // multiply the compressed RMF and the ARF to make an output RMF
```

```

if ( inputRMF.checkCompatibility(inputARF) ) {

    outputRMF = inputRMF * inputARF;

    // and write out the result copying any extra HDUs and keywords from
    // the input RMF

    Status = outputRMF.write(outfile, rmffile);

}

exit(0);
}

```

The following example shows an example program to create an RMF file.

```

#include "rmf.h"
using namespace std;

int main(int argc, char* argv[])
{

    const size_t Nenergies(1024), Nchannels(1024);
    const Real responseThreshold(1.0e-6);

    rmf Response;

    Response.AreaScaling = 1.0;
    Response.ResponseThreshold = responseThreshold;
    Response.EnergyUnits = "keV";
    Response.RMFUnits = "cm^2";

    Response.OrderGroup.resize(0);

    Response.ChannelType = "PI";
    Response.RMFVersion = "1.3.0";
    Response.EBDVersion = "1.2.0";
    Response.Telescope = "MyTelescope";
    Response.Instrument = "MyInstrument";
    Response.Detector = "NONE";
    Response.Filter = "NONE";
    Response.RMFType = "FULL";
    Response.RMFExtensionName = "MATRIX";
}

```

```

Response.EBDEExtensionName = "EBOUNDS";

// code to load the response energy ranges into
// Response.LowEnergy and Response.HighEnergy

Response.LowEnergy.resize(Nenergies);
Response.HighEnergy.resize(Nenergies);
for(size_t i=0; i<Nenergies; i++) {
    Response.LowEnergy[i] = 0.1 + i*0.01;
    Response.HighEnergy[i] = 0.1 + (i+1)*0.01;
}

// code to load the channel energy ranges into
// Response.ChannelLowEnergy and Response.ChannelHighEnergy

Response.ChannelLowEnergy.resize(Nchannels);
Response.ChannelHighEnergy.resize(Nchannels);
for(size_t i=0; i<Nchannels; i++) {
    Response.ChannelLowEnergy[i] = 0.1 + i*0.01;
    Response.ChannelHighEnergy[i] = 0.1 + (i+1)*0.01;
}

// loop over the energy ranges creating the response. In this
// example the response is assumed to be a simple gaussian

for (size_t i=0; i<Nenergies; i++) {

    Real centroid = (Response.LowEnergy[i] + Response.HighEnergy[i])/2.0;
    Real sigma = sqrt(centroid);

    vector<Real> work(Nchannels);
    calcGaussResp(sigma, centroid, responseThreshold, Response.ChannelLowEnergy,
                  Response.ChannelHighEnergy, work);

    // add to the response matrix
    Response.addRow(work, Response.LowEnergy[i], Response.HighEnergy[i]);
}

// Ensure that all arrays are calculated
Response.update();

// Convert to correct units (not required in this particular example)
Integer status = Response.convertUnits();

```



```

// Check for errors
string diagnostic = Response.check();

// Write to an output FITS file
status = Response.write("MyResponse.rsp");

return(0);
}

```

3.3.2 rmf class

```

class rmf{
public:

    Integer FirstChannel;           // First channel number

    vector<Integer> NumberGroups;    // Number of response groups for this
                                    // energy bin
    vector<Integer> FirstGroup;      // First response group for this energy
                                    // bin (counts from 0)

    vector<Integer> FirstChannelGroup; // First channel number in this group
    vector<Integer> NumberChannelsGroup; // Number of channels in this group
    vector<Integer> FirstElement;      // First response element for this group
                                    // (counts from 0)
    vector<Integer> OrderGroup;        // The grating order of this group

    vector<Real> LowEnergy;           // Start energy of bin
    vector<Real> HighEnergy;          // End energy of bin

    vector<Real> Matrix;              // Matrix elements

    vector<Real> ChannelLowEnergy;    // Start energy of channel
    vector<Real> ChannelHighEnergy;   // End energy of channel

    Real AreaScaling;                // Value of EFFAREA keyword
    Real ResponseThreshold;           // Minimum value in response

    string EnergyUnits;               // Energy units used
    string RMFUnits;                  // Units for RMF values

    string ChannelType;               // Value of CHANTYPE keyword

```

```

string RMFVersion;           // MATRIX extension format version
string EBDVersion;           // EBOUNDS extension format version
string Telescope;
string Instrument;
string Detector;
string Filter;
string RMFType;              // HDUCLAS3 keyword in MATRIX extension
string RMFExtensionName;     // EXTNAME keyword in MATRIX extension
string EBDEExtensionName;    // EXTNAME keyword in EBOUNDS extension

```

3.3.3 rmf class public methods

- Integer read(string filename)

Integer read(string filename, Integer RMFnumber)

Read the RMF file into an object. If RMFnumber is given read from the MATRIX (or SPECRESP MATRIX) and EBOUNDS extensions with EXTVER=RMFnumber. If there is only one EBOUNDS extension then that will be used.

- Integer readMatrix(string filename)

Integer readMatrix(string filename, Integer RMFnumber)

Read the MATRIX (or SPECRESP MATRIX) extension from an RMF file into an object. If RMFnumber is given read from the MATRIX (or SPECRESP MATRIX) extension with EXTVER=RMFnumber.

- Integer readChannelBounds(string filename)

Integer readChannelBounds(string filename, Integer RMFnumber)

Read the EBOUNDS extension from an RMF file into an object. If RMFnumber is given read from the EBOUNDS extension with EXTVER=RMFnumber.

- void update()

Update the FirstGroup and FirstElement arrays from NumberGroups and NumberChannels-Group, respectively.

- void initialize(const arf&)

Initialize from an arf object. Copies members in common between arfs and rmfs

- rmf& operator= (const rmf&)

Deep copy.

- `Integer NumberChannels()`

Return the number of spectrum channels.

- `Integer NumberEnergyBins()`

Return the number of response energies.

- `Integer NumberTotalGroups()`

Return the number of response groups.

- `Integer NumberTotalElements()`

Return the number of response elements.

- `Real ElementValue(Integer Channel, Integer EnergyBin)`

`Real ElementValue(Integer Channel, Integer EnergyBin,
Integer GratingOrder)`

Return the value for a particular channel, energy, and grating order.

- `vector<Real> RowValues(Integer EnergyBin)`

`vector<Real> RowValues(Integer EnergyBin,
Integer GratingOrder)`

Return the response array for a particular energy and grating order.

- `vector<Integer> RandomChannels(const Real energy,
const Integer NumberPhotons)`

`vector<Integer> RandomChannels(const vector<Real>& energy,
const vector<Integer>& NumberPhotons)`

`vector<Integer> RandomChannels(const Real energy,
const Integer NumberPhotons, Integer GratingOrder)`

`vector<Integer> RandomChannels(const vector<Real>& energy,
const vector<Integer>& NumberPhotons, Integer GratingOrder)`

Use the response matrix to generate random channel numbers for photons of given energy and grating order. For each energy, NumberPhotons are generated.

- `string disp()`

Display information about the response. - return as a string.

- `void clear()`
Clear information from the response.
- `void clearMatrix()`
Clear only the matrix information from the response.
- `string check()`
Check completeness and consistency of information in the rmf, if there is a problem then return diagnostic in string.
- `void normalize()`
Normalize the rmf so it sums to 1.0 for each energy bin.
- `void compress(const Real threshold)`
Compress the rmf to remove all elements below the threshold value.
- `void uncompress()`
Uncompress the rmf i.e. turn it into a full rectangular matrix.
- `Integer rebinChannels(grouping&)`
Rebin in channel space using the specified grouping object.
- `Integer rebinEnergies(grouping&)`
Rebin in energy space using the specified grouping object.
- `Integer shiftChannels(const Integer Start,
 const Integer End, const Real Shift)`

```
Integer shiftChannels(const Integer Start,
                     const Integer End, const Real Shift, const Real Factor,
                     bool useEnergyBounds)
```

```
Integer shiftChannels(const vector<Integer>& vStart,
                     const vector<Integer>& vEnd, const vector<Real>& vShift,
                     const vector<Real>& vFactor, bool useEnergyBounds)
```

```
Integer shiftEnergies(const Integer Start,
                     const Integer End, const Real Shift, const Real Factor)
```

```
Integer shiftEnergies(const vector<Integer>& vStart,
                     const vector<Integer>& vEnd, const vector<Real>& vShift,
                     const vector<Real>& vFactor)
```

Remap the response up or down in channels. Moves response between channels Start and End by Shift channels and stretches by Factor. If useEnergyBounds is true then Shift is assumed to be in energy, otherwise in channels.

- `Integer interpolateAndMultiply(const vector<Real>& energies,
const vector<Real>& factors)`

Multiply by a vector which may not have the same energy binning as the response.

- `Integer write(string filename)`

`Integer write(string filename, string copyfilename)`

`Integer write(string filename, string copyfilename, Integer HDUnumber)`

Write response to a RMF file. If copyfilename is given then copy from it other HDUs and other keywords in the MATRIX and EBOUNDS extensions. If HDUnumber is specified then use the MATRIX and EBOUNDS extensions with EXTVER=HDUnumber in copyfilename. Note that if the output filename exists and already has MATRIX and EBOUNDS extensions then these methods will write additional extensions.

- `Integer writeMatrix(string filename)`

`Integer writeMatrix(string filename, string copyfilename)`

`Integer writeMatrix(string filename, string copyfilename,
Integer HDUnumber)`

Write the MATRIX extension to a RMF file. If copyfilename is given then copy from it other HDUs and other keywords in the MATRIX extension. If HDUnumber is specified then use the MATRIX extension with EXTVER=HDUnumber in copyfilename. Note that if the output filename exists and already has a MATRIX extension then these methods will write an additional extension.

- `Integer writeChannelBounds(string filename)`

`Integer writeChannelBounds(string filename, string copyfilename)`

`Integer writeChannelBounds(string filename, string copyfilename,
Integer HDUnumber)`

Write the EBOUNDS extension to a RMF file. If copyfilename is given then copy from it other HDUs and other keywords in the EBOUNDS extension. If HDUnumber is specified then use the EBOUNDS extension with EXTVER=HDUnumber in copyfilename. Note that if the output filename exists and already has a EBOUNDS extension then these methods will write an additional extension.

- `rmf& operator*=(const arf&)`

Multiply current rmf by an arf.

- `rmf& operator*=(const Real&)`
Multiply current rmf by a factor.
- `rmf& operator+=(const rmf&)`
Add another rmf to the current rmf.
- `Integer checkCompatibility(const rmf&)`
Check compatibility with another rmf.
- `Integer checkCompatibility(const arf&)`
Check compatibility with an arf.
- `Integer convertUnits()`
Convert energy units from current units to keV. Valid options for the current units are keV, MeV, GeV, Hz, angstrom, cm, micron, nm.
- `void reverseRows()`
Reverse the rows. This is useful if the rows are not in increasing order of energy, which xspec requires.
- `void addRow(const vector<Real> Response,
 const Real eLow, const Real eHigh)`

`void addRow(const vector<vector<Real> > Response, const Real eLow,
 const Real eHigh, const vector<Integer> GratingOrder)`

Add a row to the response using an input response vector and energy range.
- `void substituteRow(const Integer RowNumber,
 const vector<Real> Response)`

`void substituteRow(const Integer RowNumber,
 const vector<vector<Real> > Response,
 const vector<Integer> GratingOrder)`

Substitute a row into the response using an input response vector and energy range.
- `vector<Real> multiplyByModel(const vector<Real>& model)`
Multiply a response by a vector and output a vector of pha values. The input vector is assumed to be on the energy binning.
- `vector<Real> estimatedFWHM()`
Return a vector containing the FWHM in channels for each energy. This does assume that the response has a well-defined main peak.

3.3.4 Other rmf routines

- `rmf operator* (const rmf&, const arf&)`

`rmf operator* (const arf&, const rmf&)`

Multiply an rmf by an arf.

- `rmf operator* (const rmf&, const Real&)`

`rmf operator* (const Real&, const rmf&)`

Multiply an rmf by a factor.

- `rmf operator+ (const rmf&, const rmf&)`

Add two rmfs.

- `void calcGaussResp(const Real width, const Real energ,`
`const Real threshold, const vector<Real>& ChannelLowEnergy,`
`const vector<Real>& ChannelHighEnergy, vector<Real>& ResponseVector)`

Calculate the response vector for some energy give a gaussian width. The gaussian is assumed to be in the units of energy, ChannelLowEnergy and ChannelHighEnergy. The resulting response vector can be added into a response using addRow.

- `size_t binarySearch(const Real energy, const vector<Real>& lowEnergy,`
`const vector<Real>& highEnergy)`

Return the index in the energy array containing the input energy using binary search.

3.3.5 rmft class

```
class rmft{
public:

    Integer FirstChannel;           // First channel number

    vector<Integer> NumberGroups;    // Number of response groups for this
                                    // channel bin
    vector<Integer> FirstGroup;      // First response group for this channel
                                    // bin (counts from 0)

    vector<Integer> FirstEnergyGroup; // First energy bin in this group
    vector<Integer> NumberEnergiesGroup; // Number of energy bins in this group
    vector<Integer> FirstElement;    // First response element for this group
```

```

vector<Integer> OrderGroup;           // (counts from 0)
                                     // The grating order of this group

vector<Real> LowEnergy;               // Start energy of bin
vector<Real> HighEnergy;              // End energy of bin

vector<Real> Matrix;                  // Matrix elements

vector<Real> ChannelLowEnergy;        // Start energy of channel
vector<Real> ChannelHighEnergy;       // End energy of channel

Real AreaScaling;                    // Value of EFFAREA keyword
Real ResponseThreshold;               // Minimum value in response

string EnergyUnits;                   // Energy units
string RMFUnits;                      // RMF units

string ChannelType;                   // Value of CHANTYPE keyword
string RMFVersion;                    // MATRIX extension format version
string EBDVersion;                    // EBOUNDS extension format version
string Telescope;
string Instrument;
string Detector;
string Filter;
string RMFType;                       // HDUCLAS3 keyword in MATRIX extension
string RMFExtensionName;              // EXTNAME keyword in MATRIX extension
string EBDEExtensionName;             // EXTNAME keyword in EBOUNDS extension

```

3.3.6 rmft class public methods

- `void load(rmf&)`
Load object from a standard rmf object.
- `void update`
Update the FirstGroup and FirstElement arrays from NumberGroups and NumberEnergies-Group, respectively.
- `rmft& operator= (const rmft&)`
Deep copy.
- `Integer NumberChannels()`
Number of spectrum channels
- `Integer NumberEnergyBins()`

Number of response energies

- `Integer NumberTotalGroups()`

Total number of response groups

- `Integer NumberTotalElements()`

Total number of response elements

- `Real ElementValue(Integer Channel, Integer EnergyBin)`

Return the value for a particular channel and energy.

- `vector<Real> RowValues(Integer Channel)`

Return the array for a particular channel.

- `string disp()`

Display information about the object. - return as a string.

- `void clear()`

Clear information from the object.

3.3.7 arf class

```
class arf{
public:

    vector<Real> LowEnergy;    // Start energy of bin
    vector<Real> HighEnergy;  // End energy of bin

    vector<Real> EffArea;     // Effective areas

    string EnergyUnits;       // Units for energies
    string arfUnits;          // Units for effective areas

    string Version;           // SPECRESP extension format version
    string Telescope;
    string Instrument;
    string Detector;
    string Filter;
    string ExtensionName;     // EXTNAME keyword in SPECRESP extension
```

3.3.8 arf class public methods

- `Integer read(string filename)`

`Integer read(string filename, Integer ARFnumber)`

`Integer read(string filename, Integer ARFnumber,
Integer RowNumber)`

Read file into an object. If ARFnumber is given read from the SPECRESP extension with EXTVER=ARFnumber. The third option is to read an arf from the RowNumber row of a type II file.

- `arf& operator= (const arf&)`

Deep copy.

- `Integer NumberEnergyBins()`

Return size of vector*j*Real*s*.

- `string disp()`

Display information about the arf. - return as a string.

- `void clear()`

Clear information from the arf.

- `string check()`

Check completeness and consistency of information in the arf, if there is a problem then return diagnostic in string.

- `rebin(grouping&)`

Rebin the arf using the input grouping.

- `Integer write(string filename)`

`Integer write(string filename, string copyfilename)`

`Integer write(string filename, string copyfilename, Integer HDUnumber)`

Write arf as type I file. If copyfilename is given then copy from it other HDUs and other keywords in the SPECRESP extension. If HDUnumber is specified then use the SPECRESP extension with EXTVER=HDUnumber in copyfilename. Note that if the output filename exists and already has a SPECRESP extension then these methods will write an additional SPECRESP extension.

- `arf& operator*=(const Real&)`

Multiply by a constant.

- `arf& operator+=(const arf&)`
Add another arf.
- `Integer checkCompatibility(const arf&)`
Check compatibility with another arf.
- `Integer convertUnits()`
Convert the energies on which the arf is calculated from the current units to keV. The allowed units are keV, MeV, GeV, Hz, angstrom, cm, micron, nm.

3.3.9 Other arf routines

- `arf operator+ (const arf&, const arf&)`
Add two arfs.
- `arf operator* (const arf&, const Real&)`

`arf operator* (const Real&, const arf&)`

Multiply by a constant.

3.3.10 arfII class

```
class arfII{
public:

    vector<arf> arfs;           // vector of arf objects
```

3.3.11 arfII class public methods

- `Integer read(string filename)`

`Integer read(string filename, Integer ARFnumber)`

`Integer read(string filename, Integer ARFnumber,`
 `vector<Integer> RowNumber)`

Read an ARF type II file into an object. If ARFnumber is given then read from the SPECRESP extension with EXTVER=ARFnumber. If the RowNumber array is given then read those in the extension otherwise read all the arfs.

- `arfII& operator= (const arfII&)`
Deep copy.
- `arf get(Integer number)`
Get arf object (counts from zero).
- `void push(arf ea)`
Push arf object into arfII object
- `Integer NumberARFs()`
Return the number of ARFs in the object.
- `string disp()`
Display information about the ARFs. - return as a string.
- `void clear()`
Clear information from the ARFs.
- `string check()`
Check completeness and consistency of information in the arfs, if there is a problem then return diagnostic in string.
- `Integer write(string filename)`

`Integer write(string filename, string copyfilename)`

`Integer write(string filename, string copyfilename,
Integer HDUnumber)`

Write ARFs as type II file. If copyfilename is given then copy from it other HDUs and other keywords in the SPECRESP extension. If HDUnumber is specified then use the SPECRESP extension with EXTVER=HDUnumber in copyfilename. Note that if the output filename exists and already has a SPECRESP extension then these methods will write an additional SPECRESP extension.

3.3.12 Other arfII routines

- `Integer NumberofARFs(string filename, Integer HDUumber)`

`Integer NumberofARFs(string filename, Integer HDUumber,
Integer& Status)`

Return the number of ARFS in the type II SPECRESP extension.

3.4 Table Models

3.4.1 Introduction and example

The table model file is used in xspec to provide grids of model calculations on which to interpolate when fitting a model to data. The table class can be used to create these files. The example code below sets up a grid with two parameters.

```
#include "table.h"

using namespace std;

int main(int argc, char* argv[])
{

    table test;

    // set table descriptors and the energy array

    test.ModelName = "Test";
    test.ModelUnits = " ";
    test.isRedshift = true;
    test.isAdditive = true;
    test.isError = false;

    test.Energies.resize(100);
    for (size_t i=0; i<100; i++) test.Energies[i] = 0.1+i*0.1;
    test.EnergyUnits = "keV";

    test.NumIntParams = 2;
    test.NumAddParams = 1;

    // define first parameter and give it 11 values ranging from
    // 0.0 to 2.0 in steps of 0.2.

    tableParameter testpar;

    testpar.Name = "param1";
    testpar.InterpolationMethod = 0;
    testpar.InitialValue = 1.0;
    testpar.Delta = 0.1;
    testpar.Minimum = 0.0;
    testpar.Bottom = 0.0;
    testpar.Top = 2.0;
```

```

testpar.Maximum = 2.0;

testpar.TabulatedValues.resize(11);
for (size_t i=0; i<11; i++) testpar.TabulatedValues[i] = 0.2*i;

// and push it onto the vector of parameters

test.Parameters.push_back(testpar);

// define the second parameter and give it 5 values ranging from
// 4.6 to 5.4 in steps of 0.2.

testpar.Name = "param2";
testpar.InterpolationMethod = 0;
testpar.InitialValue = 5.0;
testpar.Delta = 0.1;
testpar.Minimum = 4.6;
testpar.Bottom = 4.6;
testpar.Top = 5.4;
testpar.Maximum = 5.4;

testpar.TabulatedValues.resize(5);
for (size_t i=0; i<5; i++) testpar.TabulatedValues[i] = 4.6+0.2*i;

// and push it onto the vector of parameters

test.Parameters.push_back(testpar);

// define an additional parameter (usually the elemental abundance)
// does not require tabulated values.

testpar.Name = "addparam";
testpar.InterpolationMethod = -1;
testpar.InitialValue = 0.0;
testpar.Delta = 0.1;
testpar.Minimum = 0.0;
testpar.Bottom = 0.0;
testpar.Top = 5.0;
testpar.Maximum = 5.0;
testpar.TabulatedValues.resize(0);

// and push it onto the vector of parameters

test.Parameters.push_back(testpar);

```

```

// now set up the spectra. these are arbitrarily calculated, in a real program
// this step would read a file or call a routine.

tableSpectrum testspec;

testspec.Flux.resize(99);
testspec.ParameterValues.resize(2);

vector<Real> addFlux(99);

for (size_t i1=0; i1<11; i1++) {
    for (size_t i2=0; i2<5; i2++) {
        testspec.ParameterValues[0] = 0.2*i1;
        testspec.ParameterValues[1] = 4.6+0.2*i2;
        for (size_t j=0; j<99; j++) {
testspec.Flux[j] = testspec.ParameterValues[0]+10*testspec.ParameterValues[1];
addFlux[j] = 1.0*(i1+1)*(i2+1);
        }
        testspec.addFlux.push_back(addFlux);
        test.Spectra.push_back(testspec);
        testspec.addFlux.clear();
    }
}

// now write out the table.

test.write("test.mod");

exit(0);
}

```

3.4.2 table classes

The class for parameters:

```

class tableParameter{
public:

    string Name;                // Parameter name
    int InterpolationMethod;     // 0==linear, 1==log, -1==additional (non-interp)
    Real InitialValue;          // Initial value for fit
    Real Delta;                 // Delta for fit
    Real Minimum;               // Hard lower-limit

```

```

// (should correspond to first tabulated value)
Real Bottom;           // Soft lower-limit
Real Top;              // Soft upper-limit
Real Maximum;          // Hard upper-limit
// (should correspond to last tabulated value)
vector<Real> TabulatedValues; // Tabulated parameter values

```

and its public methods:

- `string disp()`
Display information about the table parameter - return as a string.
- `void clear()`
Clear contents of the table parameter

The class for model spectra:

```

class tableSpectrum{
public:

vector<Real> Flux;           // Model flux
vector<Real> FluxError;     // Error on Model flux
vector<Real> ParameterValues; // Parameter values for this spectrum
vector<vector<Real>> addFlux; // Model fluxes for any additional
                             // parameters
vector<vector<Real>> addFluxError; // Error on model fluxes for any
                             // additional parameters

```

and its public methods:

- `void pushaddFlux(vector<Real>)`
Push an additional parameter spectrum
- `vector<Real> getaddFlux(Integer Number)`
Get an additional parameter spectrum
- `string disp()`
Display information about the table spectrum - return as a string.
- `void clear()`
Clear contents of the table spectrum

Finally, the class for the complete table:


```

class table{
public:

    vector <tableParameter> Parameters; // Parameter information
    vector <tableSpectrum> Spectra;     // Tabulated model spectra
    string ModelName;                   // Name to use in xspec
    string ModelUnits;                   // Units (not used at present)
    int NumIntParams;                    // Dimension of interpolation grid
    int NumAddParams;                    // Number of additional parameters
    bool isError;                        // If true then model errors included
    bool isRedshift;                     // If true include redshift
    bool isAdditive;                     // If true model is additive
    vector<Real> Energies;                // Energy bins on which model is calculated
                                         // The size should be one larger than that
                                         // of the spectrum array

    string EnergyUnits;                  // Units of energy bins
    Real LowEnergyLimit;                 // Value to use for energies
                                         // below those tabulated

    Real HighEnergyLimit;                // Value to use for energies
                                         // above those tabulated

    string Filename;                     // Name of file from which table was read

```

and its public methods:

- Integer read(string filename)

Integer read(string filename, bool loadAll)

Read the table model object from filename. If loadAll is false then don't actually read in the Spectra but set up the objects.

- template <class T> Integer readSpectra(T& spectrumList)

Read in the listed Spectra if they have not already been. The class T can be vector<Integer>, valarray<Integer>, vector<size_t>, or valarray<size_t>.

- void pushParameter(tableParameter paramObject)

Push a table Parameter object

- void pushSpectrum(tableSpectrum spectrumObject)

Push a table spectrum object

- tableParameter getParameter(Integer Number)

Get a table Parameter object

3.5.2 grouping class public methods

- `grouping(vector<Integer> flaginput)`

Constructor from an integer array of flag values.

- `string disp()`

Display grouping information. - return as a string.

- `void clear()`

Clear grouping information.

- `Integer read(string filename, const Integer Number,
 const Integer First)`

Read from an ascii file of grouping factors. Each line of the file should have three numbers, the start bin, end bin, and grouping factor. The input bin numbers start at First and there are Number in total.

- `void load(const Integer BinFactor, const Integer Number)`

Set the grouping flags for Number bins with a binning factor of BinFactor.

- `Integer load(const vector<Integer>& StartBin, const vector<Integer>& EndBin,
 const vector<Integer>& BinFactor, const Integer Number,
 const Integer First)`

Set grouping flags from an array of binning information in the StartBin, EndBin and BinFactor arrays. The input bin numbers start at First and there are Number in total.

- `template <class T>Integer loadMin(const T Minimum,
 const vector<T> values)`

```
template <class T>Integer loadMin(const T Minimum,
    const Integer StartChannel, const Integer EndChannel,
    const vector<T> Values)
```

Set the grouping flags based on requiring a minimum value in each grouped bin when the values in each channel are those in the input Values array. Optionally only do this between the StartChannel and EndChannel channels.

- `bool newBin(const Integer Bin)`

Return whether Bin is the start of a group.

- `Integer size()`

Return number of bins in grouping object.

3.5.3 Other grouping routines

- `template <class T> void GroupBin(const vector<T>& inArray,
const Integer mode, const grouping& GroupInfo, vector<T>& outArray)`

`template <class T> void GroupBin(const valarray<T>& inArray,
const Integer mode, const grouping& GroupInfo, valarray<T>& outArray)`

This routine applies GroupInfo to the input inArray to create the output outArray. The behavior is determined by mode which can take five values: SumMode which adds the contents of all bins in a group; SumQuadMode which adds the bins in quadrature; MeanMode which returns the arithmetic mean of the all bins in a group; FirstEltMode which returns the value of the first bin in each group; LastEltMode which returns the value of the last bin in each group.

- `Integer readBinFactors(string filename, vector<Integer>& StartBin,
vector<Integer>& EndBin, vector<Integer>& BinFactor)`

Read a file containing grouping information and place into the arrays StartBin, EndBin and BinFactor. Each line of the file should have three numbers, the start bin, end bin, and grouping factor.

3.6 Utility routines

- `void SPreadColUnits(ExtHDU&, string, string&)`
Read the units associated with a column.
- `void SPwriteColUnits(Table&, string, string)`
Write the units associated with a column.
- `string SPstringTform(const vector<string>& Data)`
Returns the tform string for the longest string in the input vector.
- `Integer SPcopyHDUs(string infile, string outfile)`
Copy from infile to outfile all HDUs which are not manipulated by this library.
- `Integer SPcopyKeys(string infile, string outfile, string HDUname,
Integer HDUnumber)`

`Integer SPcopyKeys(string infile, string outfile, string HDUname,
string outHDUname, Integer HDUnumber, Integer outHDUnumber)`

Copy non-critical keywords from infile to outfile for HDUname extension with EXTVER HDUnumber.

- `Integer SPwriteCreator(string filename, string HDUname, string creator)`

`Integer SPwriteCreator(string filename, string HDUname, Integer HDUnumber, string creator)`

Write the creating program and version id string into the CREATOR keyword in the specified file.

- `vector<Integer> SPfindExtensions(string filename, string keyname, string value, Integer& Status);`

Find the numbers of any extensions containing keyword keyname=keyvalue

- `bool isValidXUnits(string xUnits)`

Checks whether xUnits are supported.

- `Integer calcXfactor(string xUnits, bool& isWave, Real& xFactor)`

Calculates the conversion factor for xUnits energies/wavelength to keV. If xUnits is wavelength then returns isWave as true.

- `bool isValidYUnits(string yUnits)`

Checks whether yUnits are supported.

- `Integer calcYfactor(string yUnits, bool& isEnergy, bool& perWave, Real& yFactor)`

Calculates the conversion factor for yUnits to ph/cm²/s. If yUnits contains an energy numerator (eg ergs) then returns isEnergy as true. If yUnits contains a wavelength denominator (eg micron) returns perWave as true.

- `void SPreportError(int errorNumber, string optionalString)`

Add to the error stack errorNumber along with an optional string containing additional information.

- `string SPgetErrorStack()`

Write the entire error stack into a string.

- `string SPclearErrorStack()`

Clear the error stack.

- `vector<string> SPreadStrings(const string& filename)`

Read a text file and place each row into its own element of a vector|string|.

- `vector<string> SPtokenize(const string & str, const string & delim)`

Divide a string into substrings delimited using delim.

- `string SPmatchString(const string& str,
 const vector<string>& strArray, int& nmatch)`

Partial match a string from a vector of strings.

- `bool SPstring2Real(const vector<string>& str,
 vector<Real>& value)`

Convert a vector of strings into a vector of Reals.

- `bool SPstring2Real(const string& str, Real& value)`

Convert a string into a Real.

- `bool SPstring2double(const vector<string>& str,
 vector<double>& value)`

Convert a vector of strings into a vector of doubles.

- `bool SPstring2double(const string& str, double& value)`

Convert a string into a double.

- `bool SPstring2float(const vector<string>& str,
 vector<float>& value)`

Convert a vector of strings into a vector of floats.

- `bool SPstring2float(const string& str, float& value)`

Convert a string into a float.

- `bool SPstring2Integer(const vector<string>& str,
 vector<Integer>& value)`

Convert a vector of strings into a vector of Integers.

- `bool SPstring2Integer(const string& str, Integer& value)`

Convert a string into an Integer.

- `void SPcalcShift(const vector<Real>& Low,
 const vector<Real>& High, const vector<Integer>& vStart,
 const vector<Integer>& vEnd, const vector<Real>& vShift,
 const vector<Real>& vFactor, vector<vector<size_t>>& fromIndex,
 vector<vector<Real>>& Fraction)`

Calculate factors for shifting an array

- `template <class T> void SPfind(const T& array,
 const Real& target, Integer& index)`

Find the position in the array of the target value. If array is increasing the index is the last element in array \leq target; if target $<$ array[0] then index = -1; if target \geq array[array.size()-1] then index = array.size()-1. If array is decreasing the index is the last element in array \geq target; if target $>$ array[0] then index = -1; if target \leq array[array.size()-1] then index = array.size()-1. The template class T can be either vector or valarray of Real or Integer.

- `template <class T> void SPbisect(Integer& lower, Integer& upper,
 const T& array, const Real& target, bool increasing)`

Do a bisection search between indices lower and upper on array to find target. On exit lower and upper are set to the indices which bracket target.

Chapter 4

C interface

4.1 PHA files

4.1.1 PHA structure

```
struct PHA {  
  
    long NumberChannels;           /* Number of spectrum channels */  
    long FirstChannel;             /* First channel number */  
  
    float* Pha; /*NumberChannels*/ /* PHA data */  
    float* StatError; /*NumberChannels*/ /* Statistical error */  
    float* SysError; /*NumberChannels*/ /* Statistical error */  
  
    int*   Quality; /*NumberChannels*/ /* Data quality */  
    int*   Grouping; /*NumberChannels*/ /* Data grouping */  
    int*   Channel; /*NumberChannels*/ /* Channel number */  
  
    float* AreaScaling; /*NumberChannels*/ /* Area scaling factor */  
    float* BackScaling; /*NumberChannels*/ /* Background scaling factor */  
  
    float Exposure;                /* Exposure time */  
    float CorrectionScaling;        /* Correction file scale factor */  
    int   DetChans;                /* Content of DETCHANS keyword */  
  
    int Poisserr;                  /* If true, errors are Poisson */  
    char Datatype[FLEN_KEYWORD];   /* "COUNT" for count data and */  
                                    /* "RATE" for count/sec */  
    char Spectrumtype[FLEN_KEYWORD]; /* "TOTAL", "NET", or "BKG" */  
}
```



```

char ResponseFile[FLEN_FILENAME];    /* Response filename */
char AncillaryFile[FLEN_FILENAME];    /* Ancillary filename */
char BackgroundFile[FLEN_FILENAME];    /* Background filename */
char CorrectionFile[FLEN_FILENAME];    /* Correction filename */

char ChannelType[FLEN_KEYWORD];        /* Value of CHANTYPE keyword */
char PHAVersion[FLEN_KEYWORD];        /* PHA extension format version */
char Telescope[FLEN_KEYWORD];
char Instrument[FLEN_KEYWORD];
char Detector[FLEN_KEYWORD];
char Filter[FLEN_KEYWORD];
char Datamode[FLEN_KEYWORD];

char *XSPECFilter[100];                /* Filter keywords */
};

```

4.1.2 PHA routines

- `int ReadPHATypeI(char *filename, long PHANumber, struct PHA *phastruct)`
Read the type I SPECTRUM extension from a FITS file - if there are multiple SPECTRUM extensions then read the one with EXTVER=PHANumber.
- `int ReadPHATypeII(char *filename, long PHANumber, long NumberSpectra, long *SpectrumNumber, struct PHA **phastructs)`
Read the type II SPECTRUM extension from a FITS file - if there are multiple SPECTRUM extensions then read the one with EXTVER=PHANumber. Within the SPECTRUM extension reads the spectra listed in the SpectrumNumber vector.
- `int WritePHATypeI(char *filename, struct PHA *phastruct)`
Write the spectrum to a type I SPECTRUM extension in a FITS file.
- `int WritePHATypeII(char *filename, long NumberSpectra, struct PHA **phastructs)`
Write the multiple spectra to a type II SPECTRUM extension in a FITS file.
- `int ReturnPHAType(char *filename, long PHANumber)`
Return the type of the SPECTRUM extension with EXTVER=PHANumber.
- `void DisplayPHATypeI(struct PHA *phastruct)`
Write information about the spectrum to stdout.
- `void DisplayPHATypeII(long NumberSpectra, struct PHA **phastructs)`
Write information about multiple spectra to stdout.

- `int RebinPHA(struct PHA *phastruct, struct BinFactors *bin)`
Rebin spectrum.
- `int CheckPHACounts(char *filename, long PHANumber)`
Return 0 if COUNTS column exists and is integer or COUNTS column does not exist.
- `long ReturnNumberOfSpectra(char *filename, long PHANumber)`
Return the number of spectra in the type II SPECTRUM extension which has EXTVVER equal to PHANumber.

4.2 RMF files

4.2.1 RMF structure

```

struct RMF {

    long NumberChannels;           /*Number of spectrum channels*/
    long NumberEnergyBins;         /*Number of response energies*/
    long NumberTotalGroups;        /*Total number of resp groups*/
    long NumberTotalElements;      /*Total number of resp elts*/
    long FirstChannel;             /*First channel number*/
    long isOrder;                  /*If true grating order*/
                                   /*information included*/

    long* NumberGroups; /*NumberEnergyBins*/ /*Number of resp groups for*/
                                   /*this energy bin*/
    long* FirstGroup; /*NumberEnergyBins*/ /*First resp group for this*/
                                   /*energy bin (counts from 0)*/

    long* FirstChannelGroup; /*NumberTotalGroups*/ /*First channel number in*/
                                   /*this group*/
    long* NumberChannelGroups; /*NumberTotalGroups*/ /*Num of channels in this grp*/
    long* FirstElement; /*NumberTotalGroups*/ /*First resp elt for this grp*/
                                   /*(counts from 0)*/
    long* OrderGroup; /*NumberTotalGroups*/ /*Grating order of this grp*/

    float* LowEnergy; /*NumberEnergyBins*/ /*Start energy of bin*/
    float* HighEnergy; /*NumberEnergyBins*/ /*End energy of bin*/

    float* Matrix; /*NumberTotalElements*/ /*Matrix elements*/

    float* ChannelLowEnergy; /*NumberChannels*/ /*Start energy of channel*/
    float* ChannelHighEnergy; /*NumberChannels*/ /*End energy of channel*/

```

```

float AreaScaling;                /*Value of EFFAREA keyword*/
float ResponseThreshold;          /*Minimum value in response*/

char EnergyUnits[FLEN_KEYWORD];  /*Units for energies*/
char RMFUnits[FLEN_KEYWORD];     /*Units for RMF*/

char ChannelType[FLEN_KEYWORD];  /*Value of CHANTYPE keyword*/
char RMFVersion[FLEN_KEYWORD];   /*MATRIX format version*/
char EBDVersion[FLEN_KEYWORD];   /*EBOUNDS format version*/
char Telescope[FLEN_KEYWORD];
char Instrument[FLEN_KEYWORD];
char Detector[FLEN_KEYWORD];
char Filter[FLEN_KEYWORD];
char RMFType[FLEN_KEYWORD];      /*HDUCLAS3 keyword in MATRIX*/
char RMFExtensionName[FLEN_VALUE]; /*EXTNAME keyword in MATRIX*/
char EBDEExtensionName[FLEN_VALUE]; /*EXTNAME keyword in EBOUNDS*/

};

struct RMFchan {

    long NumberChannels;          /*Number of spectrum channels*/
    long NumberEnergyBins;        /*Number of response energies*/
    long NumberTotalGroups;       /*Total number of resp groups*/
    long NumberTotalElements;     /*Total number of resp elts*/
    long FirstChannel;            /*First channel number*/
    long isOrder;                 /*If true grating order*/
                                /*information included*/

    long* NumberGroups; /*NumberChannels*/ /*Number of resp groups for*/
                                /*this channel bin*/
    long* FirstGroup; /*NumberChannels*/ /*First resp group for this*/
                                /*channel bin (counts from 0)*/

    long* FirstEnergyGroup; /*NumberTotalGroups*/ /*First energy bin in this grp*/
    long* NumberEnergyGroups; /*NumberTotalGroups*/ /*Number of energy bins in*/
                                /*this group */
    long* FirstElement; /*NumberTotalGroups*/ /*First resp elt for this grp*/
                                /*(counts from 0)*/
    long* OrderGroup; /*NumberTotalGroups*/ /*Grating order of this group*/

    float* LowEnergy; /*NumberEnergyBins*/ /*Start energy of bin*/
    float* HighEnergy; /*NumberEnergyBins*/ /*End energy of bin*/

```

```

float* Matrix;/*NumberTotalElements*/      /*Matrix elements*/

float* ChannelLowEnergy;/*NumberChannels*/  /*Start energy of channel*/
float* ChannelHighEnergy;/*NumberChannels*/ /*End energy of channel*/

float AreaScaling;                          /*Value of EFFAREA keyword*/
float ResponseThreshold;                    /*Minimum value in response*/

char EnergyUnits[FLEN_KEYWORD];            /*Units for energies*/
char RMFUnits[FLEN_KEYWORD];               /*Units for RMF*/

char ChannelType[FLEN_KEYWORD];            /*Value of CHANTYPE keyword*/
char RMFVersion[FLEN_KEYWORD];             /*MATRIX format version*/
char EBDVersion[FLEN_KEYWORD];             /*EBOUNDS format version*/
char Telescope[FLEN_KEYWORD];
char Instrument[FLEN_KEYWORD];
char Detector[FLEN_KEYWORD];
char Filter[FLEN_KEYWORD];
char RMFType[FLEN_KEYWORD];                /*HDUCLAS3 keyword in MATRIX*/
char RMFExtensionName[FLEN_VALUE];         /*EXTNAME keyword in MATRIX*/
char EBDEExtensionName[FLEN_VALUE];        /*EXTNAME keyword in EBOUNDS*/

};

```

4.2.2 RMF routines

- `int ReadRMFMatrix(char *filename, long RMFnumber, struct RMF *rmf)`
Read the RMF matrix from a FITS file - if there are multiple RMF extensions then read the one with EXTVER=RMFnumber.
- `int WriteRMFMatrix(char *filename, struct RMF *rmf)`
Write the RMF matrix to a FITS file.
- `int ReadRMFEbounds(char *filename, long EBDnumber, struct RMF *rmf).`
Read the RMF ebounds from a FITS file - if there are multiple EBOUNDS extensions then read the one with EXTVER=EBDnumber.
- `int WriteRMFEbounds(char *filename, struct RMF *rmf)`
Write the RMF ebounds to a FITS file.
- `void DisplayRMF(struct RMF *rmf)`
Write information about RMF to stdout.

- `void ReturnChannel(struct RMF *rmf, float energy, int NumberPhotons, long *channel)`
Return the channel for a photon of the given input energy - draws random numbers to return NumberPhotons entries in the channel array.
- `void NormalizeRMF(struct RMF *rmf)`
Normalize the response to unity in each energy.
- `void CompressRMF(struct RMF *rmf, float threshold)`
Compress the response to remove all elements below the threshold value.
- `int RebinRMFChannel(struct RMF *rmf, struct BinFactors *bins)`
Rebin the RMF in channel space.
- `int RebinRMFEnergy(struct RMF *rmf, struct BinFactors *bins)`
Rebin the RMF in energy space.
- `void TransposeRMF(struct RMF *rmf, struct RMFchan *rmfchan)`
Transpose the matrix.
- `float ReturnRMFElement(struct RMF *rmf, long channel, long energybin)`
Return a single value from the matrix.
- `float ReturnRMFchanElement(struct RMFchan *rmfchan, long channel, long energybin)`
Return a single value from the transposed matrix.
- `int AddRMF(struct RMF *rmf1, struct RMF *rmf2)`
Add rmf2 onto rmf1.

4.3 ARF files

4.3.1 ARF structure

```
struct ARF {

    long NumberEnergyBins;                /* Number of response energies */

    float* LowEnergy; /*NumberEnergyBins*/ /* Start energy of bin */
    float* HighEnergy; /*NumberEnergyBins*/ /* End energy of bin */

    float* EffArea;    /*NumberEnergyBins*/ /* Effective areas */

    char EnergyUnits[FLEN_KEYWORD];        /* Units for energies */
}
```

```

char arfUnits[FLEN_KEYWORD];          /* Units for effective areas */

char ARFVersion[FLEN_KEYWORD];        /* SPECRESP extension format version */
char Telescope[FLEN_KEYWORD];
char Instrument[FLEN_KEYWORD];
char Detector[FLEN_KEYWORD];
char Filter[FLEN_KEYWORD];
char ARFExtensionName[FLEN_VALUE];    /* EXTNAME keyword in SPECRESP */

};

```

4.3.2 ARF routines

- `int ReadARF(char *filename, long ARFnumber, struct ARF *arf)`
Read the effective areas from a FITS file - if there are multiple SPECRESP extensions then read the one with EXTVER=ARFFnumber.
- `int WriteARF(char *filename, struct ARF *arf)`
Write the ARF to a FITS file.
- `void DisplayARF(struct ARF *arf)`
Write information about ARF to stdout.
- `int AddARF(struct ARF *arf1, struct ARF *arf2)`
Add arf2 onto arf1.
- `long MergeARFRMF(struct ARF *arf, struct RMF *rmf)`
Multiply the ARF into the RMF.

4.4 Binning and utility

4.4.1 BinFactors structure

```

struct BinFactors {

    long NumberBinFactors;

    long *StartBin;
    long *EndBin;
    long *Binning;

};

```

4.4.2 Binning and utility routines

- `int SPReadBinningFile(char *filename, struct BinFactors *binning)`
Read an ascii file with binning factors and load the binning array.
- `int SPSetGroupArray(int inputSize, struct BinFactors *binning,
int *groupArray)`
Set up a grouping array using the BinFactors structure.
- `int SPBinArray(int inputSize, float *input, int *groupArray, int mode,
float *output)`
Bin an array using the information in the grouping array.
- `void SPsetCCfitsVerbose(int mode)`
Set the CCfits verbose mode.
- `int SPcopyExtensions(char *infile, char *outfile)`
Copy all HDUs which are not manipulated by this library.
- `int SPcopyKeywords(char *infile, char *outfile, char *hduname,
int hdunumber)`
Copy all non-critical keywords for the hdunumber instance of the extension hduname.

Appendix A

Building programs using heasp

To build a C++ program using the heasp library you need to use the standard heasoft tool i.e. hmake. This requires a Makefile in the following specific format.

```
HD_COMPONENT_NAME      = heacore

HD_COMPONENT_VERS      =

HD_CXXTASK             = myprogram

HD_CXXTASK_SRC_cxx     = myprogram.cxx

HD_CXXFLAGS            = ${HD_STD_CXXFLAGS} -Wno-deprecated

HD_CXXLIBS             = ${HD_LFLAGS} ${HD_STD_CXXLIBS} -l${HEASP} \
                        ${XLIBS} ${SYSLIBS}

HD_INSTALL_TASKS       =

include ${HD_STD_MAKEFILE}
```

Here myprogram.cxx is the file containing the main routine. Any other C++ source files required can be added to the same line. This will build an executable file in the current directory. The default hmake install option is disabled but if the executable is to be placed in a particular place that command can be added to the HD_INSTALL_TASKS line.

Appendix B

Ftools and Heasp

The following table lists ftools that operate on spectra or responses and the related HEASP routines. The read and write routines apply in all cases so are not included in the table. In some, relatively simple, cases the ftool equivalent could be performed by directly getting and setting class members.

Ftool	corresponding HEASP C++ routines
addarf	arf::operator+=, arf::operator+
addrmf	rmf::operator+=, rmf::operator+
cmppha	phaII::get
cmprmf	rmf::compress
dmpmf	directly access rmf class members
gcorpha	pha::shiftChannels
gcorrmf	rmf::shiftChannels
marfrmf	rmf::operator*=, rmf::operator*
rbrmf	grouping::load, rmf::rebinChannels, rmf::rebinEnergies
arf2arf1	arfII::get
ascii2pha	directly set pha class members
chkarf	arf::check, arfII::check
chkpha	pha::check, phaII::check
chkrmf	rmf::check
flx2xsp	directly set pha and rmf class members
flx2tab	directly set table class members
grppha	grouping::load, pha::setGrouping
grppha2	phaII::get, grouping::load pha::setGrouping, phaII::push
mathpha	pha::operator+=, pha::operator+, pha::operator*=
mkftrsp	directly set rmf class members
rbrpha	grouping::load, pha::setGrouping, pha::rebinChannels
rsp2rmfarf	directly get and set rmf and arf class members
sdss2xsp	directly set pha and rmf class members
sprbnarf	grouping::load, GroupBin

Appendix C

Error Codes

- 1 : NoSuchFile : Cannot find the file specified.
- 2 : NoData : A column read has no members.
- 3 : NoChannelData : The SPECTRUM has no Channel column and no channel data can be constructed.
- 4 : NoStatError : The SPECTRUM has no statistical error column and POISSERR=F.
- 5 : CannotCreate : Cannot create a new file.
- 6 : NoEnergyLo : The ENERG_LO column in an ARF or RMF file has no data.
- 7 : NoEnergyHi : The ENERG_HI column in an ARF or RMF file has no data.
- 8 : NoSpecresp : The SPECRESP column in an ARF has no data.
- 9 : NoEboundsExt : There is no EBOUNDS extension in an RMF file.
- 10 : NoEmin : The E_MIN column in an RMF file has no data.
- 11 : NoEmax : The E_MAX column in an RMF file has no data.
- 12 : NoMatrixExt : There is no MATRIX extension in an RMF file.
- 13 : NoNgrp : The N_GRP column in an RMF file has no data.
- 14 : NoFchan : The F_CHAN column in an RMF file has no data.
- 15 : NoNchan : The N_CHAN column in an RMF file has no data.
- 16 : NoMatrix : The MATRIX column in an RMF file has no data.
- 17 : CannotCreateMatrixExt : The output MATRIX extension cannot be created.
- 18 : CannotCreateEboundsExt : The output EBOUNDS extension cannot be created.

- 19 : InconsistentGrouping : The grouping information size is different from that of the array to which it is being applied.
- 20 : InconsistentEnergies : The energy information differs between the objects which are being compared.
- 21 : InconsistentChannels : The channel information differs between the objects which are being compared.
- 22 : InconsistentUnits : The units information differs between the objects which are being compared.
- 23 : UnknownXUnits : The wavelength or energy units are not supported.
- 24 : UnknownYUnits : The flux units are not supported.
- 25 : InconsistentNumelt : The RMF MATRIX extension NUMELT keyword is inconsistent with the actual number of response elements.
- 26 : InconsistentNumgrp : The RMF MATRIX extension NUMGRP keyword is inconsistent with the actual number of response groups.
- 27 : InconsistentNumTableParams : The wrong number of parameters were given to table::getValues.
- 28 : TableParamValueOutsideRange : A parameter value was given to table::getValues which is outside the tabulated range.

Appendix D

Change log

D.1 v1.10

D.1.1 General

- Changed definition of Real from float to double.
- Added SPstring2double and SPstring2float to convert from string to double and float.
- Added SPfind and SPbisect routines to search for the position of a target value within an array.
- Added SPfindExtensions to return the numbers of extensions with a given value of some keyword.
- Added chapter on building programs using the heasp library.

D.1.2 pha, phaII

- Added selectChannels to select a subset of the pha channels.
- Added getMinCountsGrouping to get the grouping using a minimum number of counts per bin
- Added getMinSNGrouping to get the grouping using a minimum S/N ratio per bin. Optionally also uses a background pha file.

D.1.3 rmf

- Added multiplyByModel to matrix multiply the response by a vector to output a vector of pha values.
- Added estimatedFWHM to estimate the FWHM in channels for each energy range.

- Added `binarySearch` to return the index in the energy array for an input energy

D.1.4 `arf` and `arfII`

- Added `NumberOfARFs` to return the number of ARFs in the type II SPECRESP extension.

D.1.5 `table`

- Added `FluxError` and `addFluxError` to store errors on tabulated data when available.
- Added `LowEnergyLimit` and `HighEnergyLimit` to store values to be used when input energies are below and above, respectively, the tabulated energies.
- Added `Filename` to store name of file from which the table was read.
- Added option not to read all the Spectra but just set up the objects. Added a new method `readSpectra` which then loads the requested Spectra.
- Added `getValues` to return the interpolated spectrum based on the input parameter values.

D.1.6 `grouping`

- Corrected flag to be +1 for start of a bin, -1 for continuation, and 0 for ignore.
- Added `loadMin` which sets the grouping flag based requiring a minimum value in each grouped bin for the input array of values.

D.2 `v1.03`

D.2.1 `General`

- Added `SPstring2Real` and `SPstring2Integer` functions to convert vectors of strings into vectors of Reals and Integers, respectively.

D.2.2 `rmf`

- Added `interpolateAndMultiply` which multiplies the `rmf` by a vector which may not be on the same energy binning as the `rmf`.

D.3 `v1.02`

D.3.1 `General`

- Added `SPwriteCreator` routine to write the CREATOR keyword.

- Added SPreadStrings routine to read a text file into a vector of strings.
- Added SPtokenize routine to divide a string into substrings.
- Added SPmatchString routine to partial match a string from a vector of strings.
- Added SPstring2Real routine to convert a string to a Real.
- Added SPstring2Integer routine to convert a string to an Integer.
- Added SPcalcShift routine to calculate factors used for shifting an array.

D.3.2 pha, phaII

- Added shiftChannels options to include a stretch by specified factor, to deal with multiple shifts at the same time, and to allow the shift to be specified in energy instead of channels.

D.3.3 rmf

- Added RandomChannels options to use multiple input energies, each with a different number of output photons.
- Added an uncompress method to turn a compressed matrix into the full rectangular form.
- Added shiftChannels options to include a stretch by specified factor, to deal with multiple shifts at the same time, and to allow the shift to be specified in energy instead of channels.
- Added a *= and * operators to multiply by a constant.
- Added substituteRow method to replace a given row in the rmf. Note that this is inefficient so should not be used repeatedly to construct a new rmf.

D.3.4 arf

- Added a rebin method.
- Added *= and * operators to multiply by a constant.

D.4 v1.01

D.4.1 General

- Added unit conversions through calcXfactor and calcYfactor routines.
- Added a global SErrorStack to improve error reporting. Entries are added to the stack using SPreportError and can be retrieved using SPgetErrorStack which returns a string. SPClearErrorStack resets the stack.

- Added modifications to all classes to handle case where user writes an extension of some type into a file which already contains an extension of the same type. Now writes the new extension with an EXTVER keyword set to one more than the highest EXTVER of other extensions of the same type in the file.
- Made checkCompatibility routines consistent across classes and added a check for units.

D.4.2 pha, phaII

- Overloaded +, += for pha objects to add them and *= to multiply by a constant.
- Added version of pha::rebinChannels which allows control of the method for calculating the new StatError.
- Added pha::shiftChannels to shift channels.
- Added missing write of the DETCHANS keyword/column for type II PHA files.
- Fixed problem in C wrappers for spectra with arrays containing identical values.

D.4.3 rmf

- Replaced the compressLine function with the rmf::addRow method. Added the reverseRows method to use in cases where the original energy bins are not in increasing order. Added calcGaussResp function to calculate the gaussian response for one row of a response matrix.
- Added rmf::clearMatrix method to wipe only the response matrix part of the rmf object.
- Added rmf::shiftChannels to shift channels.
- Added support for grating orders to the rmf class.
- Corrected error in rmf when reading a file with MATRIX as a fixed length vector column.
- Fixed a counting from 0 or 1 bug in rmf::RowValues.

D.4.4 table

- Added table::read method.
- Added table::reverseRows method to reverse the order of the Energy, Flux and addFlux vectors. This may be necessary if input is in wavelengths and convertUnits has been used.